

The pdfpages Package*

Andreas MATTHIAS
amat@kabsi.at

2002/01/27

Abstract

This package makes it easy to insert pages of external PDF documents. It is based on PDF \LaTeX and does *not* work with \LaTeX .

Contents

1	Introduction	1
2	Usage	1
2.1	Package Options	1
2.2	Commands	1
2.3	The Layout	6
3	Required Packages	6
4	Acknowledgment	7

1 Introduction

Creating PDF documents it is sometimes useful to insert pages of other, external PDF documents. This can be done with the `\includegraphics` command from the `graphics` package. But a simple `\includegraphics{doc.pdf}` normally produces ‘Overfull \hbox ’ and ‘Overfull \vbox ’ warnings, because the size of the inserted pages does not match the print space.

The `pdfpages` package makes it easy to insert pages of external PDF documents without worrying about the print space. It even gives you the possibility to arrange several logical pages onto each sheet of paper. (Like ‘psnup’.)

2 Usage

2.1 Package Options

```
\usepackage[<options>]{pdfpages}
```

*This file has version number v0.2e, last revised 2002/01/27.

- $\langle option \rangle$ – **final**: Inserts pages. This is the default.
- draft**: Does not insert pages, but prints a box and the filename instead.

2.2 Commands

`\includepdf` Inserts pages of an external PDF document.

`\includepdf [key=val]{filename}`

- $\langle key=val \rangle$ – A comma separated list of options using the $\langle key \rangle = \langle value \rangle$ syntax.
- $\langle filename \rangle$ – Filename of the PDF document.

The following list describes all possible options of `\includepdf`. All options are using the $\langle key=value \rangle$ syntax. If options are marked with ‘*changed*’ on the left margin, their syntax or meaning has changed since pdfpages v0.1i. New options are marked with ‘*new*’.

- Main options:

pages Selects pages to insert. The argument is a comma separated list containing page numbers (`pages={3,5,6,8}`), ranges of page numbers (`pages={4-9}`) or any combination. To insert empty pages use `{}`.

E.g.: `pages={3,{},8-11,15}` will insert page 3, an empty page, and pages 8, 9, 10, 11, and 15.

Page ranges are specified by the following syntax: $\langle m \rangle - \langle n \rangle$. This selects all pages between $\langle m \rangle$ and $\langle n \rangle$. Omitting $\langle m \rangle$ defaults to the first page, omitting $\langle n \rangle$ defaults to the last page of the document.

E.g.: `pages=-` will insert *all* pages of the document.

(Default: `pages=1`)

changed **nup** Puts multiple logical pages onto each sheet of paper. The syntax of this option is: `nup= $\langle xnup \rangle \times \langle ynup \rangle$` . Where $\langle xnup \rangle$ and $\langle ynup \rangle$ specify the number of logical pages in vertical and horizontal direction, which are arranged on each sheet of paper. (Default: `nup=1x1`)

changed **landscape** Specifies the format of the sheet of paper (*not* of the logical pages). Either ‘true’ or ‘false’ (or no value, which is equivalent to ‘true’). (Default: `landscape=false`)

- Layout options:

new **delta** Puts some horizontal and vertical space between the logical pages. The argument should be two dimensions, separated by space. See chapter 2.3 and figure 1. (Default: `delta=0 0`).

offset Displaces origin of the inserted pages. The argument should be two dimensions, separated by space. See chapter 2.3 and figure 1. (Default: `offset=0 0`)

frame Puts a frame around each logical page. Either ‘true’ or ‘false’ (or no value, which is equivalent to ‘true’). (Default: `frame=false`)

new **column** Pdfpages normally uses ‘row-major’ layout, where successive pages are placed in rows along the paper. The **column** option changes the output into a ‘column-major’ layout, where successive pages are arranged in columns down the paper. Either ‘true’ or ‘false’ (or no value, which is equivalent to ‘true’). (Default: **column=false**)

new **columnstrict** By default the last page is not set in a strict ‘column-major’ layout, if the logical page does not fill up the whole page. The **columnstrict** option forces a strict ‘column-major’ layout for the last page. Either ‘true’ or ‘false’ (or no value, which is equivalent to ‘true’). (Default: **columnstrict=false**)

1	4	
2	5	
3		

columnstrict=true

1	3	5
2	4	

columnstrict=false

openright This option puts an empty page before the first logical page. In combination with **nup=2x1**, **nup=2x2**, etc., this means that the first page is on the right side. The same effect can be achieved with the **pages** option, if an empty page is inserted in front of the first page. Either ‘true’ or ‘false’ (or no value, which is equivalent to ‘true’). (Default: **openright=false**)

pagecommand Declares L^AT_EX commands, which are executed on each sheet of paper. (Default: **pagecommand={\thispagestyle{empty}}**)

turn By default pages in landscape format are displayed in landscape orientation (if the PDF viewer supports this). With **turn=false** this can be prohibited. Either ‘true’ or ‘false’ (or no value, which is equivalent to ‘true’). (Default: **turn=true**)

new **noautoscale** By default pages are scaled automatically. This can be suppressed with the **noautoscale** option. In combination with the **scale** option (from **graphicx**) you has full control over the scaling process. Either ‘true’ or ‘false’ (or no value, which is equivalent to ‘true’). (Default: **noautoscale=false**)

new **fitpaper** Adjusts the paper size to the one of the inserted document. Either ‘true’ or ‘false’ (or no value, which is equivalent to ‘true’). (Default: **fitpaper=false**)

- Hypertext options:

changed **link** Inserted pages become a target of a hyperlink. The name of the link is ‘*filename*’.*page number*’. The file extension of *filename* must not be stripped. Either ‘true’ or ‘false’ (or no value, which is equivalent to ‘true’). (Default: **link=false**)

linkname Changes the default linkname created by the option **link**. Instead of *filename* the value of this option is used. E.g. **linkname=mylink** produces the linknames ‘mylink’.*page number*’. (Default: **linkname=filename**’.*page number*)

thread Combines pages to an article thread. Either ‘true’ or ‘false’ (or no value, which is equivalent to ‘true’). (Default: **thread=false**)

threadname Several threads are distinguished by their names. By default this name is equal to the filename. It can be changed with this option. This is useful if the same file is inserted twice or more times and should not be combined to one single thread. (Default: `threadname=<filename>`)

linktodoc Lets the inserted pages be hyperlinks to the document from which they were extracted. Either ‘true’ or ‘false’ (or no value, which is equivalent to ‘true’). (Default: `linktodoc=false`)

- Additional hypertext options:

linkfit Specifies the way the viewer displays a linked page. This option changes the default behavior of the option `link`. Possible values are: `fitb`, `fith`, `fitv`, `fitr`, `xyz zoom <integer>`, etc. These are destinations (`\pdfdest`) like they are described in [1]. (Default: `linkfit=fitr`)

linktodocfit By default the option `linktodoc` opens the page in ‘Fit in Window’ view. Another view can be specified with this option. Possible values are the legal PDF tokens: `/FitH <top>`, `/FitV <left>`, etc. (See [2] for more details.) (Default: `linktodocfit=/Fit`)

linkfilename Sets the name (with path) of the file to be linked to by the option `linktodoc`. You will hardly ever need this option. (Default: `linkfilename=<filename>`)

- Obsolete options:

`deltax` Puts some horizontal space between the logical pages. The argument should be one dimension, separated by space. (Default: `deltax=0`).

`deltay` Puts some vertical space between the logical pages. The argument should be one dimension, separated by space. (Default: `deltay=0`).

Internally the command `\includepdf` makes use of the `\includegraphics` command from the `graphicx` (actually `graphics`) package. This way it is possible to use all the options of `\includegraphics`, too. Options which are not interpreted by `\includepdf` are passed directly to `\includegraphics`.


Especially the ‘trim’ and ‘clip’ options of `\includegraphics` are quite useful, if only parts of a page should be inserted. (Maybe to cut off the header and footer of the inserted pages.) Just use the ‘trim’ and ‘clip’ options as if they were options of `\includepdf`. They will be passed to `\includegraphics` internally.

`\includepdfmerge` Inserts pages of several external PDF documents.

`\includepdfmerge[<key=val>]{<file-page-list>}`

`<key=val>` – A comma separated list of options using the `<key>=<value>` syntax.

`<file-page-list>` – `<filename>` [`,<page spec>`] [`,<file-page-list>`]
A comma separated list of filenames and optional `<page spec>` specifiers. A `<page spec>` can be everything the option `pages` accepts.



— physical sheet of paper	$\mathbf{\delta}=\langle \delta x \rangle \langle \delta y \rangle$
— logical pages	$\mathbf{offset}=\langle off_x \rangle \langle off_y \rangle$
--- centered position	

Figure 1: Layout

The `\includepdfmerge` command uses the same options as `\includepdf` with one exception. The option `pages` has no meaning for `\includepdfmerge`. Instead the `<page spec>` specifier is used to specify which pages should be inserted. The `<page spec>` specifier accepts the same values as the `pages` option. If no `<page spec>` specifier is given, only the first page will be inserted.

`\includepdfset` If you need the same options for `\includepdf` all the time, it is possible to define global options with `\includepdfset`. The argument of `\includepdfset` is a comma separated list of options, using the `<key>=<value>` syntax. These options are processed each time `\includepdf` is called. Local options (passed as an optional argument directly to `\includepdf`) are overwriting global options:

```
\includepdfset{<global options>}
\includepdf[<local options>]{pdf-file}
```

Only options specific to this package can be made global by `\includepdfset`. Options of the `graphicx` package are not concerned.

`\threadinfodict` A thread information dictionary contains information about the thread, such as its title, author, and creation date. Use the macro `\threadinfodict` to set these entries. This macro has one argument taking the thread information dictionary in low-level PDF commands. See [2] for more information. This macro can be redefined. E. g.:

```
\renewcommand*{\threadinfodict}
{/I << /Title (My first thread) /Author (That's me!) >>}
```

2.3 The Layout

The default layout can be changed by the options `delta` and `offset`. Figure 1 shows the meaning of these options.

The inserted logical pages are being centered on the sheet of paper by default. To displace them use the `offset` option, which argument should be two dimensions. E. g. `offset=10mm 14mm` means that the logical pages are displaced by 10 mm in horizontal direction and by 14 mm in vertical direction.

By default logical pages are being arranged side by side. To put some space between them, use the `delta` option, whose argument should be two dimensions. Figure 1 shows the meaning of `delta`.

The layout options `delta` and `offset` *always* refer to a sheet of paper in portrait orientation. No matter whether you have set the `landscape` option to `true`, or not.

If you are confused about horizontal (`x`) and vertical (`y`) directions, just set the option `turn=false`. Now your PDF viewer shows the pages in the *same* orientation as in figure 1. And the options `delta` and `offset` have the *same* meaning as in figure 1. Regardless of any other options.

3 Required Packages

The `pdfpages` package requires the following packages:

eso-pic CTAN:macros/latex/contrib/supported/ms/contrib/ Download the whole `ms/` directory, because `eso-pic.sty` requires `everyshi.sty` from that directory.

graphicx, **ifthen**, **calc** These packages belong to the standard L^AT_EX distribution.

Furthermore it requires a recent version of:

pdftex.def <http://www.tug.org/applications/pdftex/pdftex.def>

Since pdfT_EX, Version 3.14159-1.00a-pretest-20010806, PDF import has improved a lot. This results in much smaller file sizes, faster processing and the intuitively correct treatment of landscape pages. The latest version of pdfT_EX can be found at: <ftp://ftp.muni.cz/pub/tex/local/cstug/thanh/pdftex>.

4 Acknowledgment

I would like to thank ROLF NIEPRASCHK and HEIKO OBERDIEK for their useful hints and suggestions. As well as ROSS MOORE, who encouraged me to implement the hypertext features.

References

- [1] Hàn Thé Thành, Sebastian Rahtz, Hans Hagen, *The pdfT_EX user manual*, <http://www.tug.org/applications/pdftex/pdftex-s.pdf>
- [2] *PDF Reference*, Second Edition, Adobe Systems Incorporated, <http://partners.adobe.com/asn/developer/acrosdk/DOCS/PDFRef.pdf>